

IMC

MPLS VPN Manager 7.3 (E0501P02)

© Copyright 2015, 2017 Hewlett Packard Enterprise Development LP

Table of Contents

1. [What's New in this Release](#)
 2. [Problems Fixed in this Release](#)
 3. [MVM Software Distribution Contents](#)
 4. [Installation Prerequisites](#)
 5. [Port Usage](#)
 6. [Typical Installation](#)
 7. [Upgrade Installation](#)
 8. [Removing MVM](#)
 9. [Known Problems](#)
-

What's New in this Release

IMC MVM 7.3 (E0501P02) can be upgraded from only IMC MVM 7.3 (E0501).

>The following lists all features released in IMC MVM 7.2 (E0402) and later versions.

Features released in IMC MVM 7.3 (E0501P02)

1. The MPLS VPN Management can identify UPEs or SPEs in the group after you specify a UPE or SPE peer group for a SPE.
2. The L2VPN Management supports the RESTful interface for querying L2VPN information.
3. The VSI name column is added to the AC undeployment page of the L2VPN Management.
4. The L2VPN Management automatically discovers VPN services after you import PEs to the component.
5. The MPLS VPN Management supports VSRs.

Features released in IMC MVM 7.3 (E0501)

1. none.

Features released in IMC MVM 7.2 (E0402P02)

- Support for EXP traffic monitoring was added in MPLS VPN component.

Features released in IMC MVM 7.2 (E0402)

- Source IP can be specified in P2P Ping on MPLS VPN Topology.

[[Table of Contents](#)]

Problems Fixed in This Release

IMC MVM 7.3 (E0501P02) fixes the following problems, including all bugs fixed in IMC MVM 7.2 (E0402) and later versions.

Resolved Problems in IMC MVM 7.3 (E0501P02)

1. IMC does not receive any alarms when the traffic of an LSP exceeds the alarm threshold.
2. After you change the MAC address of a CE and perform the synchronization operation, the MAC address of the CE remains unchanged.

Resolved Problems in IMC MVM 7.3 (E0501)

1. The tips displayed when you click a link of a PE on the IP topology page do not contain the VPN information of the link.
2. It costs a long time to open the Import P or Import PE page when the following conditions are met:
 - Log in to the IMC that runs on Linux and Oracle.
 - Click Import P or Import PE on the Region Management page for the first time.

Resolved Problems in IMC MVM 7.2 (E0402P02)

1. The V2 reports in MPLS VPN Management cannot be opened.

Resolved Problems in IMC MVM 7.2 (E0402)

1. none.

[[Table of Contents](#)]

MVM Software Distribution Contents

The IMC MVM 7.3 (E0501P02) distribution list contains the following files and folders:

1. **MVM\manual\readme_mvm_7.3 (E0501P02).html** - This file
2. **MVM\windows\install** - The IMC installation program for Window

3. **MVM\linux\install** - The IMC installation program for Red Hat Enterprise Linux

[[Table of Contents](#)]

Installation Prerequisites

Server Requirements

The following are the minimum hardware requirements and supported software programs to run IMC:

- Minimum hardware requirements
 - Pentium 4 3.0 GHz processor
 - 8 GB of RAM
 - 100 GB hard disk space

- Operating system (Versions marked X64 are recommended):
 - Windows Server 2008 X64 with Service Pack 2
 - Windows Server 2008 R2 X64 with Service Pack 1
 - Windows Server 2012 X64 with KB2836988
 - Windows Server 2012 R2
 - Red Hat Enterprise Linux 5.5 X64 (Enterprise and Standard versions only)
 - Red Hat Enterprise Linux 5.9 X64 (Enterprise and Standard versions only)
 - Red Hat Enterprise Linux 6.1 X64 (Enterprise and Standard versions only)
 - Red Hat Enterprise Linux 6.4 X64 (Enterprise and Standard versions only)
 - Red Hat Enterprise Linux 6.5 X64 (Enterprise and Standard versions only)
 - Red Hat Enterprise Linux 7.x X64 (Enterprise and Standard versions only)

- VMware:
 - VMware Workstation 6.5.x
 - VMware Workstation 9.0.x
 - VMware ESX Server 4.x
 - VMware ESX Server 5.x

- Hyper-V:
 - Windows Server 2008 R2 Hyper-V
 - Windows Server 2012 Hyper-V

- Database
 - Microsoft SQL Server 2005 Service Pack 4 (Windows only)
 - Microsoft SQL Server 2008 Service Pack 3 (Windows only)
 - Microsoft SQL Server 2008 R2 Service Pack 2 (Windows only)
 - Microsoft SQL Server 2012 Service Pack 1 (Windows only)
 - Microsoft SQL Server 2014 (Windows only)
 - Oracle 11g Release 1 (Linux only)
 - Oracle 11g Release 2 (Linux only)
 - Oracle 12c Release 2 (64-bit) (Linux only)
- IMC Platform Compatibility
 - IMC Platform version: IMC PLAT 7.3 (E0506) and its patches.

Note: 64-bit operating systems are recommended over 32-bit operating systems because of the larger amount of available memory for applications.

Note: Optimal hardware requirements vary with scale, other management factors, and are specific to each infrastructure. Please consult HP, or your local account teams and precise requirements can be provided.

[[Table of Contents](#)]

TCP Port Usage

The MVM Server will BIND to and use the following TCP/IP Ports.

Component	Subcomponent	Protocol	Port	Configurable	Use	Server	Client	Notes
MVM	--	UDP	161	Yes	Used to access network elements through SNMP.	IMC MVM Server	All IMC users	None
MVM	--	UDP	162	Yes	Used to accept SNMP Traps	IMC MVM Server	All IMC users	None

					from network elements.			
MVM	--	TCP	22	Yes	SSH/SFTP port, which the configuration center uses to back up and restore the device software and configuration file through SSH/SFTP.	IMC MVM Server	All IMC users	None
MVM	--	TCP	20/21	Yes	FTP port, which the configuration center uses to back up and restore the device software and configuration file through FTP.	IMC MVM Server	All IMC users	None
MVM	--	TCP	23	Yes	Telnet port, which the resource management module, ACL management module, and configuration center use to access the device through Telnet.	IMC MVM Server	All IMC users	None
MVM	--	ICMP	--	Yes	ICMP port, which the resource management module uses to discover devices and check the	IMC MVM Server	All IMC users	None

						reachability of the devices.			
MVM	--	UDP	69	Yes		IMC-specific TFTP daemon.	IMC MVM Server	All IMC users	None
MVM	--	TCP	80	Yes		Used to launch the web network management system of the device.	IMC MVM Server	All IMC users	None
MVM	--	TCP	443	Yes		HTTPS port, which the virtual network management module uses to obtain VMware virtual network data in SSL.	IMC MVM Server	All IMC users	None
MVM	--	TCP	8080	Yes		IMC-specific web server for HTTP protocol (can be changed when installation).	IMC MVM Server	All IMC users	None
MVM	--	TCP	8443	Yes		IMC-specific web server for HTTPS protocol (can be changed when installation).	IMC MVM Server	All IMC users	None
MVM	--	TCP	8800	Yes		IMF listening port.	IMC MVM Server	All IMC users	None
MVM	--	TCP	1433	Yes		SQL Server database listening port (Windows only).	IMC MVM Server	All IMC users	None
MVM	--	UDP	6666	Yes		iNode location	IMC MVM	All IMC	None

					listening port.	Server	users	
--	--	--	--	--	--------------------	--------	-------	--

[[Table of Contents](#)]

Typical Installation

Before installing MVM, make sure the IMC is installed correctly. To install MVM, click **Install** button on the **Monitor** tab of the Intelligent Deployment Monitoring Agent, then select the *components* sub-directory of the upgrade package, and click **OK** button to launch the installation wizard.

For detailed installation instructions, please refer to IMC deployment guides.

[[Table of Contents](#)]

Upgrade Installation

Please follow these instructions for upgrading the IMC:

1. Back up the IMC database on the Environment tab in the Deployment Monitoring Agent.
2. Stop IMC in the Deployment Monitoring Agent.
3. Click **Install** button in the **Monitor** tab of the Deployment Monitoring Agent.
4. Select the *windows/install/components* subdirectory of the upgrade package, and click **OK** button.
5. After the installation finishes, the Deployment Monitoring Agent will detect the components that need to be upgraded. Click **OK** button to start upgrading the components.
6. In Distributed deployment mode, upgrade all components deployed on every subordinate server.
7. After all components are updated, start all processes in the Deployment Monitoring Agent window.

[[Table of Contents](#)]

Removing MVM

You can remove MVM component through the intelligent deployment monitoring agent. To do this, follow these steps:

1. In the Intelligent Deployment Monitoring Agent window, select **Stop IMC** on the **Monitor** tab to stop all processes of IMC.
2. On the **Deploy** tab, right-click the MVM component, and select **Uninstall the Component** from the shortcut menu.
3. A dialog box appears, indicating that the component was successfully removed. Click **OK**.

[[Table of Contents](#)]

Known Problems

- On MPLS VPN Manager Desktop, the pie chart in the VPN Resources does not display normally.
- On MPLS VPN Manager, the line chart in the SA Traffic Report does not display the configured threshold lines.
- MPLS Management cannot raise an alarm when the MPLS traffic exceeds the threshold.
- The minimum average rate and average rate in NTA traffic analysis statistics are greatly different from the actual values.

[[Table of Contents](#)]

Issued: Dec. 2017

© Copyright 2015, 2017 Hewlett Packard Enterprise Development LP